

How to Use a Settings XML File

Each of the sample Settings XML File contains both a Settings XML File and the media files to display the sample. The easiest way to implement a Settings XML File is to do the following:

- **Use the example** on your Android device and get it running with the sample media.
- **Modify the sample Settings XML file** to create your own Settings file.

How to Use these Examples

To use these examples, do the following:

1. Open the folder containing the example you want to use.
2. Copy the folder named “videokiosk” to the /sdcard on your Android device [For more information, refer to the “How to Install Video Kiosk” Tutorial on our site at: <https://burningthumb.com/apps/video-kiosk/tutorials/>]
3. Launch Video Kiosk.

Video Kiosk will now play the pre-configured example. This will give you an idea of how to set up a display similar to the one you want to create.

How to Use Create and deploy a Settings XML File

The easiest way to create a settings xml file is to just make a copy of one of the sample xml files in this kit and edit it. Follow these steps:

1. **Edit the example XML File.** In a Text Editor, edit the sample XML settings file of your choice.
 - The XML Schema is documented in the **Video Kiosk Users Manual – Appendix C Video Kiosk XML Settings.**
 - The XML Tags correspond to Video Kiosk’s settings. For more information about each setting, refer to the **Video Kiosk Users Manual – Configuring the Settings** [<https://burningthumb.com/wp-content/uploads/video-kiosk-android-users-manual.pdf>]
 - For more information about editing an XML File, refer to <https://burningthumb.com/how-to-guides/>
2. **Save and Name the File XML.** Ensure that you’ve named the file “videokiosk.settings.xml”.
3. **Move the File.** Move the file onto the device either using a USB cable or over the cloud using the Cloud Update feature. [For more information, refer to the “How to use the Cloud Update Feature” Tutorial on our site at: <https://burningthumb.com/apps/video-kiosk/tutorials/>]

4. Launch Video Kiosk.

How to Use modify the Device Settings

To modify your settings:

1. Modify the Settings XML File and download to your devices. The device's settings will update automatically – no re-start required.

Note: Your Android device settings can be changed either using the XML or by changing the settings manually on the device. We recommend that you use one method or the other, but not a hybrid of both. If you use a hybrid of both, you run the risk of overwriting your manual changes with the values in you Setting XML file